

Enterprise Azure Configuration Guide

Version 8.7.0 Revision 1.0.0



Table of Contents

1. Introduction	. 3
2. About Enterprise Azure	. 3
Main Differences to Our Standard (Non-Cloud) Product	. 3
Why use Enterprise Azure?	. 4
3. Azure Deployment Models.	. 4
4. Accessing Microsoft Azure	. 4
5. Azure Management	. 4
Accessing the Azure Portal	. 5
Azure PowerShell & Azure CLI.	. 5
6. Deploying Enterprise Azure From the Marketplace	. 5
7. Accessing the Appliance	. 11
Accessing the Appliance using the WebUI	. 11
WebUI Menu Options	12
Appliance Security	12
Security Mode	12
Passwords	13
Checking For Updates	13
Appliance Licensing	14
Enterprise Azure Non-standard WebUI Menu Options	14
Accessing the Appliance using SSH	15
Generating SSH Keys	15
Accessing the Appliance from Linux	16
Accessing the Appliance from Windows using PuTTY.	16
8. Configuration Examples	. 17
High Availability	. 17
Key Concepts	. 17
Implementing HA in Azure	18
1 – Load Balancing Web Servers, HA Configuration, 1 subnet, layer 7	20
2 – Load Balancing Web Servers, HA Configuration, 1 subnet, layer 7 with SSL Termination	30
3 – Load Balancing Web Servers, HA Configuration, 1 subnet, layer 7 (Manual Configuration) with SSL	43
Termination	
4 – Load Balancing Web Servers, Single Appliance, 2 subnets, layer 4 NAT Mode	45
5 – Load Balancing Web Servers, Single Appliance, 2 subnets, layer 7 with TProxy	50
9. Testing – General Comments	52
Testing Load Balanced Services	52
Diagnosing VIP Connection Problems	52
	53
Using Reports & Log Files	54
	э4 г 4
п. Loaupalancer.org Technical Support	э4

1. Introduction

Microsoft Azure is a comprehensive set of cloud services that developers and IT professionals use to build, deploy and manage applications through Microsoft's global network of data centers. It allows services to be deployed as and when required. Charges are made for what is used making it an extremely flexible and cost effective solution. The Loadbalancer.org Enterprise Azure cloud based load balancer allows customers to rapidly deploy and configure a feature rich load balancing solution within the Azure cloud.

2. About Enterprise Azure

Enterprise Azure is a fully featured Application Delivery Controller (ADC) / Load Balancer designed specifically for Azure. The core software is based on customized versions of Centos 6.x/RHEL 6.x, Linux 4.9.x, LVS, HA-Linux, HAProxy, Pound, STunnel & Ldirectord.

Enterprise Azure can be deployed as a single instance although we always recommend that 2 appliance's are deployed as an HA clustered pair to avoid introducing a single point of failure.

Enterprise Azure is based on the same code base as our main hardware/virtual product. This means that Enterprise Azure supports many of the same features as the hardware & virtual based products. There are certain differences due to the way the Microsoft Azure environment works. The main differences are listed below.

Main Differences to Our Standard (Non-Cloud) Product

- 1. Layer 4 DR mode is *not* currently supported.
- 2. In Azure, you should configure your HA pair *first* before setting up your load balanced services. This is different to the recommendation for our hardware/virtual products and is due to the way HA is handled. In our standard product, when a failover occurs, the *same* VIP address is brought up on the passive device. In Azure, in order to minimize the time taken for the failover a different approach is used. When creating a VIP on an Azure HA pair, 2 private IPs must be specified one for the VIP when it's active on the Primary and one for the VIP when it's active on the Secondary. The IPs for the VIP on the Primary & Secondary are selected using drop-downs within the VIP configuration screen. An Azure load balancer is used in front of the Loadbalancer.org HA pair to direct inbound connections to the active appliance. Both Primary & Secondary appliances must be in the same Availability Set or deployed within the same Availability Zone / split across 2 different Availability Zones. Please refer to High Availability for more information on configuring an HA pair.

The private IPs for the VIP on the Primary & Secondary are selected using drop-downs within the VIP configuration screen. These drop-downs are only displayed *after* the pair is configured. They are populated with the IPs that are assigned to the network interface using the WebUI option: *Local Configuration > Network Interface Configuration*.

Adding VIPs after creating an HA pair (RECOMMENDED) – If you add VIPs after creating an HA pair, you'll be prompted for both IPs. Add the IPs you intend to use for the VIPs to the local interface on both Primary & Secondary and they'll be available in the drop-downs.

Note

Creating an HA pair after configuring VIPs on the Primary – If you add a Secondary appliance and create an HA pair after adding VIPs to the Primary appliance, the floating IPs that were automatically configured for each VIP must first be removed using the WebUI option: *Cluster Configuration > Floating IPs* and then added to the network interface instead. This will ensure that these IPs appear in the drop-downs mentioned above. You'll also need to configure IPs in a similar way on the Secondary device so that corresponding Secondary IPs can be selected for each VIP using the drop-downs.

- Layer 4 NAT mode where the default gateway on the load balanced real servers is required to be the load balancer is *not* supported. Routing rules for the real server subnet must be changed instead. Please refer to Configuration Example 4 for more details.
- 4. Layer 7 SNAT mode with TProxy enabled where the default gateway on the load balanced real servers is required to be the load balancer is *not* supported. Routing rules for the real server subnet must be changed instead. Please refer to Configuration Example 5 for more details.

Why use Enterprise Azure?

Microsoft Azure's load balancer provides basic load balancing functionality but is limited in several areas. Loadbalancer.org's Enterprise Azure load balancer provides the following additional features & advantages:

- 1. Supports comprehensive Layer 7 load balancing.
- 2. Load balances both Azure based and non-Azure based servers.
- 3. Supports Round Robin and Least Connection connection distribution algorithms.
- 4. Supports customizable timeouts for custom applications beyond those offered by Azure.
- 5. Supports comprehensive back-end server health-check options.
- 6. Enables fallback servers to be configured and invoked when all load balanced servers/services fail.
- 7. Provides extensive real time and historical statistics reports.
- 8. Supports session distribution based on actual server load (utilizing Loadbalancer.org's feedback agent which is available for both Linux & Windows).
- 9. Supports SSL Termination.
- 10. Supports Microsoft RDP Cookie based persistence.
- 11. Supports full integration with Microsoft Remote Desktop Services Connection Broker.

Note For a full feature comparison please refer to our Enterprise Azure product page.

3. Azure Deployment Models

The Azure platform currently supports both the original Classic model and the latest Resource Manager model. To simplify the deployment and management of resources, Microsoft recommends that the Resource Manager model is used for new resources, and, if possible, existing resources are re-deployed through Resource Manager. For a more detailed comparison of Classic and Resource Manager models, please refer to this URL.

4. Accessing Microsoft Azure

To start using Microsoft Azure, you'll need an Azure account. If you don't already have one you can create one at the following URL: https://azure.microsoft.com/en-gb/free/.

5. Azure Management

Azure resources can be managed in 3 ways:

- Azure Portal
- Azure PowerShell

Azure CLI

Accessing the Azure Portal

The Azure Portal is available here.

Azure PowerShell & Azure CLI

Information on how to obtain, install and configure PowerShell is available here.

Information on how to obtain, install and configure Azure CLI is available here.

6. Deploying Enterprise Azure From the Marketplace

- 1. Login to the Azure Portal.
- 2. Select Virtual Machines.
- 3. Click Add.

Configure the Basics



- 1. Configure the Subscription & Resource group settings according to your requirements.
- 2. Enter a suitable name for the instance, e.g. LB1.
- 3. Select the required *Region*.
- 4. Configure the Availability options according to your requirements.

For an HA clustered pair, both VMs must be in the same Availability Set or deployed within Note the same Availability Zone / split across 2 different Availability Zones. Please refer to High Availability for more details on setting up an HA pair.

- 5. Select the required Image to do this, click See all images then enter "Loadbalancer.org" in the Marketplace search box and hit <ENTER>.
- 6. The following options are available:
 - Load Balancer ADC Fully featured appliance, hourly based billing
 - Load Balancer ADC 10G (licensed for up to 20Gbps throughput)
 - Load Balancer ADC 1G (licensed for up to 4Gbps throughput)
 - Load Balancer ADC BYOL Fully featured appliance, one time payment (*)
 - Load Balancer ADC BYOL (purchase & apply either the 1G or the 10G license)
 - Note (*) Azure infrastructure costs apply.

The BYOL version will work completely unrestricted for 30 days without any Notelicense applied. During this period, only Azure usage charges will apply. After the
30 days, the trial will still function, but no configuration changes will be possible until the license is applied.

7. Select the required Size - this can be changed by expanding the drop-down and selecting from the recently used or recommended image sizes. Or alternatively by clicking See all sizes and choosing from the expanded list of options.

N	ote

The Image size required depends on the anticipated workload. For more details on the image size that best suits your requirements, please refer to the following Microsoft links:

 Note
 Sizes for Virtual Machines and Linux Virtual Machine Pricing. The standard A1 with 1 vCPU &

 1.75GB RAM is primarily meant for PoC deployments and low traffic websites and application.

 For a non PoC deployment we recommend at least 2 vCPUs and 3.5GB RAM. For further

 For a non PoC deployment we recommend at least 2 vCPUs and 3.5GB RAM. For further help and advice please contact support@loadbalancer.org.

8. Select the required Authentication type – a Password or an SSH Public key can be used.

Please refer to Generating SSH Keys for more details on creating and using SSH keys. Note

- 9. If using password authentication, enter a suitable Username & Password.
- 10. Click Next: Disks >.

Configure Disks

Disk option	ns				
OS disk typ	e* 🛈	Standard SSD	Standard SSD		
Encryption	type *	(Default) Encryp	tion at-rest with a plat	form-managed key	\sim
Enable Ultr	a Disk compatibility 🛈	🔿 Yes 💿 No)		
		Ultra Disk compa	tibility is not available	for this VM size and location.	
Data disks					
You can ad temporary	d and configure additio disk.	onal data disks for your vir	tual machine or attach	existing disks. This VM also con	nes with a
LUN	Name	Size (GiB)	Disk type	Host caching	
Create and	attach a new disk	Attach an existing disk			

1. Select the required OS disk type – by default this is set to **Standard SSD**, this can be changed if required. Typically, the default setting is appropriate for most deployments.

Note

✓ Advanced

Information on the various disk types available in Azure can be found here. Comparative disk pricing is available here.

- 2. Select the required *Encryption type*.
- 3. Click Next : Networking >.

Configure Networking

Network interface

When creating a virtual machine, a network interface will be created for you.

Virtual network * 🕠	QS-RG1-VNET1	\sim
	Create new	
Subnet * 🕕	Public-Subnet (10.1.3.0/24)	\sim
	Manage subnet configuration	
Public IP 🕡	(new) LB1-publicIP	\sim
	Create new	
NIC network security group 🕕	O None	
	O Basic	
	Advanced	
	() This VM image has preconfigured NSG rules	
	The selected subnet 'Public-Subnet (10.1.3.0/24)' is already associated to a network security group 'VNET1-Public-Subnet-nsg'. We recommend managing connectivity to this virtual machine via the existing network security group instead of creating a new one here.	
Configure network security group *	VNET1-Public-Subnet-nsg	\sim
Accelerated networking 🗊	The selected image does not support accelerated netwo	rking.

Load balancing

You can place this virtual machine in the backend pool of an existing Azure load balancing solution. Learn more 🖻

1. Configure the Virtual network, Subnet & Public IP settings according to your requirements.

- NotePublic IP addresses can be either Basic or Standard SKU the default is Basic. When setting
up HA (see High Availability), the Public IP SKU and the load balancer SKU must match to
enable backend pools to be configured. For more information on setting up public IP
addresses please click here.
- 2. Configure the Network Security Group settings according to your requirements.

Note

Microsoft recommends that where possible Network Security Groups are associated with subnets rather than individual interfaces since this simplifies management.

If you choose to create a new NSG rather than selecting an existing one, the following inbound rules are included by default: Inbound rules 1010: HTTP_access Any Custom (TCP/9080) 1020: HTTPS_access Any Custom (TCP/9443) 1030: default-allow-ssh Any SSH (TCP/22) + Add an inbound rule

- These inbound rules are required for managing the load balancer
- The rules can be edited by clicking the *Create new* link under the network security group drop-down
- Specify additional inbound rules for the ports used for your load balanced applications, e.g. TCP 80 and TCP 443 if you're load balancing web servers, TCP 3389 if you're load balancing RDP etc.
- To specify additional inbound rules, click **Add an inbound rule**. The example below shows additional ports TCP/80 (for load balanced HTTP web server traffic) and TCP/443 (for load balanced HTTPS web server traffic).

Inbound rules 🕕 1010: HTTP access Anv Custom (TCP/9080) 1020: HTTPS_access Anv Custom (TCP/9443) 1030: default-allow-ssh Anv SSH (TCP/22) 1040: Port80 Any HTTP (TCP/80) 1050: Port443 Any HTTPS (TCP/443) + Add an inbound rule

Note The rules can also be edited after the NSG is created.

- Once the required rules have been defined, click **OK**.
- 3. Under the "Load Balancing" section, if you have already configured an Azure load balancer in preparation for configuring an HA pair, ensure the *Place this virtual machine behind an existing load balancing solution?* check-box is enabled, then set *Load balancing options* to **Azure load balancer** and select the relevant load balancer. Alternatively, the Azure load balancer can be created later, in which case leave the check-box unchecked.

Note When deploying an HA pair of Loadbalancer.org instances, they must be deployed behind an Azure load balancer. For more information please refer to High availability.

4. Click Next : Management >.

Configure Management

- 1. Configure the Management Settings according to your requirements.
- 2. Click Next : Advanced >.

Configure Advanced Options

- 1. Configure the Advanced Settings according to your requirements.
- 2. Click Next : Tags >.

Configure Tags

NAME	VALUE	RESOURCE	
Environment	✓ : Test	✓ 11 selected	✓
	✓ :	✓ 11 selected	\sim

- 1. Configure Tags according to your requirements.
- 2. Click Next: Review & Create >.

Review & Create

1. Review all details, terms and settings, enter your *Name*, *Preferred e-mail address* and *Preferred phone number* in the fields provided and if you're happy to proceed, click **Create**.

If validation completes successfully, the load balancer instance will now be deployed

Enable IP Forwarding (If Required)

If you'll be configuring layer 4 NAT mode services, or layer 7 services with TProxy, ensure that IP forwarding is enabled. This allows the VM to accept traffic that is not addressed to itself, i.e. the return traffic from the load balanced servers to the client that passes via the load balancer. For an HA pair, this must be done on *both* VMs.

To enable IP forwarding:

- 1. In the Azure Management Portal, select the *Virtual Machines* option, click on the newly deployed Load Balancer VM, click on *Networking* and then select the network interface attached to the load balancer, then click *IP configurations*.
- 2. Ensure that IP forwarding is enabled as shown below:

ipconfig1	IPv4	Primary	10.1.3.4 (Dynamic)	51.105.53.141 (LB1-Public-IP)	
Name	IP Version	Туре	Private IP address	Public IP address	
Search I	P configuratior	IS			
Subnet *			Public-Subnet (10.1.3.0/25)		\sim
IP configura	ations				
Virtual netwo	ork		QS-VNET1		
IP forwardin	9		Disabled Enabled		
IP forwardi	ng settings				

7. Accessing the Appliance

Accessing the Appliance using the WebUI

In a browser, navigate to the Public IP address or FQDN on port 9443, i.e.

https://<Public IP Address>:9443

or

https://<FQDN>:9443

Note To configure an FQDN in Azure under the Resource Manager model please refer to this link.

You'll receive a warning about the certificate as it's a self signed cert not related to an Internet based CA. Confirm you want to continue and a login prompt will be displayed. Use the following default credentials:

Username: loadbalancer Password: loadbalancer

Note

To change the password for the 'loadbalancer' account, use the WebUI option: *Maintenance* > *Passwords*.

Once logged in, the WebUI is displayed:



WebUI Menu Options

System Overview - Displays a graphical summary of all VIPs, RIPs and key appliance statistics Local Configuration - Configure local host settings such as IP address, DNS, system time etc. Cluster Configuration - Configure load balanced services such as VIPs & RIPs Maintenance - Perform maintenance tasks such as service restarts and taking backups View Configuration - Display the saved appliance configuration settings Reports - View various appliance reports & graphs Logs - View various appliance logs Support - Create a support download, contact the support team & access useful links

Live Chat - Start a Live Chat session with one of our Support Engineers

Appliance Security

Note

For full details of all security related features, please refer to Appliance Security Features.

Security Mode

To control how the appliance is accessed and which features are enabled, 3 security modes are provided:

• Secure - (default) - in this mode:

- the WebUI is accessible on HTTPS port 9443. If you attempt to access the WebUI on HTTP port 9080 you will be redirected to HTTPS port 9443
- access to the Local Configuration > Execute shell command menu option is disabled
- the ability to edit the firewall script & the lockdown wizard is disabled
- 'root' user console & SSH password access are disabled
- Custom in this mode, the security options can be configured to suit your requirements
- Secure Permanent this mode is the same as Secure but the change is irreversible

Important Only set the security mode to Secure - Permanent if you are 100% sure this is what you want!

To configure the Security Mode:

- 1. Using the WebUI, navigate to: Local Configuration > Security.
- 2. Select the required *Appliance Security Mode* if **Custom** is selected, configure the additional options according to your requirements.
- 3. Configure the *HTTPS Port for Web User Interface*, *Web Interface SSL Certificate* and *Ciphers to use* according to your requirements.
- 4. Click Update.

Passwords

The password for the '**loadbalancer**' WebUI user account and the '**root**' Linux user account are set during the Network Setup Wizard. These can be changed at any time.

1 - the 'root' Linux account

As explained above, 'root' user console & SSH password access are disabled by default. If enabled, the 'root' password can be changed at the console, or via an SSH session using the following command:



\$ sudo su

2 - the 'loadbalancer' WebUI account

This can be changed using the WebUI menu option: *Maintenance > Passwords*.

Checking For Updates

Once you have access to the WebUI, we recommend that you use the online update feature to ensure that you're running the very latest version of the appliance. To check for updates, use the WebUI option: *Maintenance* > *Software Update* and click the **Online Update** button. If updates are available, you'll be presented with a list of

changes that are included in the update. To start the update, click the second **Online Update** button at the bottom of the screen. Updates are incremental, so repeat the process until you're informed that no more updates are available.

Appliance Licensing

If you've deployed the BYOL version of the appliance, by default it runs as a 30 day trial and is completely unrestricted during this time. After 30 days, the appliance continues to work but it's no longer possible to make changes to the configuration. When a license is purchased, you'll be provided with a license key file by our sales team. This must then be installed on your appliance. To install the license, use the WebUI option: *Local Configuration > License Key* to browse to and select the license file provided. Once selected, click **Install License Key** to apply the license. We recommend that you should check for updates *before* applying the license key.

Enterprise Azure Non-standard WebUI Menu Options

Enterprise Azure has some differences to the standard hardware/virtual product range due to the way the Microsoft Azure environment works. The menu options that work differently are detailed below. For all others please refer to our main Administration Manual.

1) Local Configuration > Network Interface Configuration

IP Addr	ess Assignment		
		eth0 40 GB/s	
eth0	10.1.6.4/24 10.1.6.10/24		MTU 1500 bytes
			Configure Interfaces

This menu option works in a very similar way to the standard product range, although please note the following:

- On initial deployment, a single IP private address is allocated (either static or dynamic depending on the chosen setting)
- Additional addresses can be added as shown (10.1.6.10/24) this is required when you require multiple VIPs on different IP addresses
- To add an additional IP address, enter the new address below the existing address as shown in the example above, then click **Configure Interfaces**

Important	If an IP address is added, you'll also need to add the same IP address to the Network Interface on the load balancer VM via the Azure portal. If this is not done, Azure will not be aware of the new address.
Important	If the IP address allocated to the VM on initial deployment (normally the first in the list) is changed, make sure that you add the same address to the VMs in Azure. If this is not done, you'll loose connectivity to the VM.

Accessing the Appliance using SSH

When the appliance is deployed, *Authentication type* must be set to either **SSH Public key** or **Password**. When set to **SSH Public Key**, a key pair must be manually generated outside of the Azure environment using tools such as ssh-keygen under Linux and PuttyGen under Windows. Once the key pair is generated, the public key must be copied into the *SSH public key* field at VM deployment, and the private key is then used on the SSH client machine to access the VM.

Generating SSH Keys

The steps below show how to generate SSH key pairs using Linux and Windows.

Using Linux

STEP 1 - Generate a keypair using ssh-keygen

All Distros:

ssh-keygen -q -t rsa -b 2048 -f <output filename>

e.g.

```
# ssh-keygen -q -t rsa -b 2048 -f AzureKeys
```

When prompted, enter a pass-phrase, or leave empty for no passphrase:

```
Enter passphrase (empty for no passphrase):
Enter same passphrase again:
```

2 files are created:

- AzureKeys this is the Private Key file and is used on the SSH client machine
- AzureKeys.pub this is the Public Key file, the contents are copied into the SSH public key field when the VM is deployed

Using Windows

STEP 1 – Install PuTTY

- 1. Download PuTTY from here.
- 2. Run the installer.

STEP 2 – Use PuTTYgen to generate a Public/Private key pair

1. Browse to the PuTTY program folder and run PuTTYgen.

😵 PuTTY Key Generator		? X
<u>File K</u> ey Con <u>v</u> ersions <u>H</u> elp		
Кеу		
No key.		
A. 12		
Actions		
Generate a public/private key pair	G	enerate
Load an existing private key file		Load
Save the generated key	Save public key Save	private key
Parameters		
Type of key to generate: SSH-1 (RSA)	© SSH-2 <u>D</u> SA	
Number of <u>b</u> its in a generated key:	20	48

- 2. Click the Generate button.
- 3. As directed, move the mouse around to create random keys.
- 4. Once generated, click the Save public key and Save private key buttons to save the keys.

Accessing the Appliance from Linux

Start SSH specifying the private key file and login as the user defined when deploying the VM, e.g.

Using the IP address:

ssh -i /root/AzureKeys lbuser@1.2.3.4

Or using the fqdn:

ssh -i /root/AzureKeys lbuser@fqdn

Note To configure an FQDN in Azure under the Resource Manager model please refer to this link.

Accessing the Appliance from Windows using PuTTY

- 1. Run PuTTY.
- 2. Expand the SSH section and select *Auth* as shown below.

😵 PuTTY Configurati	on	? <mark>×</mark>
Category:		
- Terminal	^	Options controlling SSH authentication
Bell Features		Bypass authentication entirely (SSH-2 only)
Window Appearance		Attempt authentication using Pageant
Behaviour Translation		Attempt TIS or CryptoCard auth (SSH-1) Attempt "keyboard-interactive" auth (SSH-2)
Selection Colours		Authentication parameters
Connection	ш	Allow attempted changes of usemame in SSH-2
Proxy Telnet		Private <u>key</u> file for authentication: Browse
SSH		
Auth		
-X11		
Bugs	-	
About	<u>H</u> elp	Open <u>C</u> ancel

- 3. Click **Browse** and select the private key created earlier.
- 4. Click **Open** to start the SSH session.
- 5. Login using the username specified when deploying the instance, no password will be required.

To enable full root access, the following command can be used once logged in to the appliance via SSH:

Note

\$ sudo su

8. Configuration Examples

This section presents 4 example configurations that illustrate how the load balancer is deployed. Web Servers are used in the examples, although the same concepts apply to other applications.

High Availability

We recommend that 2 appliance's are deployed as an HA clustered pair to avoid introducing a single point of failure. In Azure, you should configure your HA pair *FIRST* before setting up your load balanced services.

Key Concepts

- 1. In our standard hardware / virtual product, when a failover occurs, the *same* VIP address is brought up on the passive device. In Azure, in order to minimize the time taken for the failover a different approach is used.
- 2. In Azure, when creating a VIP on an HA pair, **2** private IPs must be specified one for the VIP when it's active on the Primary and one for the VIP when it's active on the Secondary.
- 3. An Azure load balancer is used in front of the Loadbalancer.org HA pair to direct inbound connections to the *active* appliance.

4. Both Primary & Secondary appliances must be in the same Availability Set or deployed within the same Availability Zone / split across 2 different Availability Zones.

Note

If you're using Availability Zones rather than Availability Sets, then a standard SKU Azure load balancer *must* be used. The standard SKU has a published SLA and the cost depends on the amount of data processed and the number of load balancing rules as explained here. The Basic SKU is free, but comes with no published Azure SLA.

If you have already configured a single appliance and now want to add a Secondary appliance to create an HA pair, the following approach can be taken:

Note

If your existing appliance has not been deployed in an Availability Set or Zone, you'll have to redeploy the instance because instances cannot be moved into a set or zone after creation. In this case, please refer to Configuration Example 1 or Configuration Example 2.

- 1. Deploy an additional Loadbalancer.org VM to be the Secondary, make sure it's in the same Availability Set or deployed within the same Availability Zone / split across 2 different Availability Zones.
- 2. On the Primary appliance, using the WebUI option: Cluster Configuration > Floating IPs, remove the floating IPs that were automatically configured for each VIP, then using the WebUI option: Local Configuration > Network Interface Configuration add the same addresses to the network interface instead. This will ensure that these IPs appear in the drop-downs used to setup the VIP(s) when in HA mode as illustrated here.
- 3. On the Secondary appliance, using the WebUI option: *Local Configuration > Network Interface Configuration* add corresponding IPs for each VIP. This will ensure that these IPs appear in the drop-downs used to setup the VIP(s) when in HA mode.
- 4. Follow Step 2 to 6 starting here.
- 5. Using the WebUI on the Primary appliance, ensure that the *Virtual Service IP address & Secondary IP Address* fields are set correctly for each VIP. As explained in Main Differences to Our Standard (Non-Cloud) Product, these drop-downs are used to specify the IP address used for the VIP when active on the Primary and when active on the Secondary.
- 6. Follow Step 7 here.
- 7. Follow Step 10 & 11 starting here.

Implementing HA in Azure

The following diagram shows how HA is configured in Azure. As shown, two Loadbalancer.org VMs are configured as a clustered pair in combination with an Azure load balancer.



- LB1 and LB2 are configured as an HA pair. In this mode, one device is active (typically the Primary appliance) and the other is passive (typically the Secondary appliance).
- The private IPs for the VIP on the Primary & Secondary are selected using drop-downs within the VIP configuration screen. These drop-downs are only displayed once the pair is configured. They are populated with the IPs that are assigned to the network interface using the WebUI option: *Local Configuration > Network Interface Configuration*.
- The probe service on TCP port 6694 is up on the active appliance (LB1) and down on the passive appliance (normally LB2), The active appliance responds with **200 OK**.

- The Azure load balancer probes port 6694 on LB1 and LB2 and then forwards traffic to the active load balancer appliance (normally LB1).
- If the Primary appliance fails for any reason, the passive appliance will detect this, become active and bring up the probe service on port 6694. In turn, the Azure load balancer detects this and will then forward traffic to the Secondary device (LB2).
- If your configuration includes VIPs with multiple ports or if you have multiple VIPs you'll need to setup multiple Load balancing rules to map from the Azure load balancer's Frontend IP to the appropriate Backend Pool and appropriate port. Also, you may need to setup multiple Frontend IP Configurations & Backend Pools depending on whether your VIPs share the same IP or have unique IP addresses, and whether the load balanced servers are common between VIPs or unique. The same Health-probe should be used for all Load balancing rules.

1 – Load Balancing Web Servers, HA Configuration, 1 subnet, layer 7

This example demonstrates how to configure an HA pair of load balancers and then configure a layer 7 VIP to load balance 2 web servers. The Loadbalancer.org instances are deployed in the same Availability Set and a Basic SKU Azure load balancer is used to route connections to the active appliance.

Step 1 – Deploy 2 x Loadbalancer.org VMs – one to be the Primary, the other to be the Secondary

1. Please refer to Deploying Enterprise Azure From the Marketplace. Ensure that both load balancer VMs are in the same Availability Set.

Step 2 – Verify Network Security Group Settings

- 1. Ensure that your Network Security Group(s) permit the following communication between the 2 VMs:
 - TCP port 22 (SSH)
 - UDP port 6694 (heartbeat)
 - ICMP Ping

Note These requirements are covered by default within the same Virtual Network. Please refer to this link for more information refer to this link for more information on default rules.

- 2. Ensure that your Network Security Group(s) permit the following inbound communication from the Azure load balancer to both VMs:
 - TCP port 6694 (Azure load balancer health probe)

Note This requirement is covered by default within the same Virtual Network. Please refer to this link for more information an elefentiation in the same Virtual Network. this link for more information on default rules.

Step 3 – Add the IP Address to be used for the VIP to the Primary & Secondary using the Azure Portal

- 1. In the Azure Portal select Virtual Machines.
- 2. Select the Primary VM.
- 3. Select Networking, then click the Network Interface.
- 4. Select IP Configurations.

5. Click Add.

Name *	
WebCluster1	\checkmark
Туре	
Primary Secondary	
Primary IP configuration already exists	
Private IP address settings	
Allocation	
Dynamic Static	
IP address *	
10.1.3.80	~
Public IP address	
Disassociate Associate	

- Enter a suitable name for the IP address, e.g. WebCluster1
- Set Private IP address Allocation to Static
- Enter an appropriate IP address (this must tally with the address to be used for your VIP on the Loadbalancer.org appliance), e.g. 10.1.3.80
- Click OK
- Now repeat steps 1-5 on the Secondary VM for the VIP using a corresponding (but different) IP address, e.g. 10.1.3.81.

Step 4 – Add the IP Address to be used for the VIP to the Primary & Secondary using the Appliance WebUI

Primary Appliance

- On the Primary, navigate to the WebUI option: Local Configuration > Network Interface Configuration
- Add the IP you intend to use for the VIP, use CIDR notation, e.g. 10.1.3.80/24

Secondary Appliance

- On the Secondary, navigate to the WebUI option: Local Configuration > Network Interface Configuration
- Add the IP you intend to use for the VIP, use CIDR notation, e.g. 10.1.3.81/24

Step 5 – Add & Configure the Azure Load Balancer

- 1. First, add the Azure Load Balancer.
 - In the Azure Portal select Load balancers
 - Click Add

Subscription *	Loadbalancer.org Pay-As-You-Go
Resource group *	QS-RG1 V
	Create new
Instance details	
Name *	AzureLB 🗸
Region *	(Europe) UK South
Type * 🕡	🔿 Internal 💿 Public
SKU * 🥫	🔿 Standard 💿 Basic
	i Microsoft recommends Standard SKU load balancer for production workloads. Learn more about pricing differences between Standard and Basic SKU a
Tier *	Regional Global
Public IP address	
Public IP address * 🔅	● Create new ○ Use existing
Public IP address name *	WebClusterPublicIP 🗸
Public IP address SKU	Basic
IP address assignment *	🔘 Dynamic 💿 Static
Add a public IPv6 address 🔅	No Yes

- Configure the Subscription & Resource group settings according to your requirements
- Enter a suitable *Name* for the instance, e.g. AzureLB
- Select the required *Region*
- If deploying within a private network set *Type* to Internal, if it's public facing select Public
- Set SKU to Basic

This configuration example uses a **Basic** SKU Azure load balancer. Configuration Example 2 uses a **Standard** SKU Azure load balancer. Please note the following when deciding which option to choose:

• If you have deployed your Primary & Secondary instances in an Availability Set then either the Basic or Standard SKU can be used

Note

- If you have deployed your Primary & Secondary instances using Availability Zones, then the Standard SKU must be used
- The Basic SKU is free, rates apply to the Standard SKU
- The Standard SKU has a published SLA, the Basic SKU does not
- Microsoft recommends the Standard SKU load balancer for production workloads
- Configure the Public IP address settings (for external deployments) or the Virtual Network settings (for internal deployments) according to your requirements

the Frontend IP Configuration in the Load balancer menu.

- Click Next : Tags >
- Configure the Tags according to your requirements
- Click Next : Review + Create >
- Once validated, review the settings and click Create
- 2. Next, create the Backend Pool(s).
 - In the menu for the load balancer, click Backend pools
 - Click Add

Name *
WebCluster1 ✓
Virtual network 🕕
QS-RG1-VNET1 (QS-RG1)
Associated to 🕕
Virtual machines V
IP Version IPv4 IPv6
Virtual machines You can only attach virtual machines in uksouth that have a basic SKU public IP configuration or no public IP configuration. All virtual machines must be in the same availability set and all IP configurations must be on the same virtual network.
+ Add × Remove

Virtual machine $\uparrow\downarrow$	IP Configuration $\uparrow \downarrow$	Availability set \uparrow_{\downarrow}
No virtual machines selected		

- Enter an appropriate Name, e.g. WebCluster1
- Select the required Virtual Network
- Under Associated to select Virtual machines
- Select the required_ IP version_, e.g. IPv4
- Click Add

🔎 Filter by name		Location == uksouth	Virtual network == 0	QS-RG1-VNET1
\blacksquare Virtual machine \uparrow_\downarrow	Resource group \uparrow_\downarrow	IP Configuration $~\uparrow_\downarrow$	Availability set \uparrow_{\downarrow}	Tags
LB1	QS-RG1	ipconfig1 (10.1.3.4)	AS1	-
LB2	QS-RG1	ipconfig1 (10.1.3.5)	AS1	-
🔽 LB1	QS-RG1	WebCluster1 (10.1.3.80)	AS1	-
✓ LB2	QS-RG1	WebCluster1 (10.1.3.81)	AS1	-

- Ensure that both load balancer VMs are selected as shown in the example above (LB1 & LB2), and that the IP addresses selected correspond to the VIP on each appliance (10.1.3.80 & 10.1.3.81)
- Click Add

Virtual machines

You can only attach virtual machines in uksouth that have a basic SKU public IP configuration or no public IP configuration. All virtual machines must be in the same availability set and all IP configurations must be on the same virtual network.

+ Add ×	Remove		
Virtual machine	\uparrow_{\downarrow}	IP Configuration $\uparrow \downarrow$	Availability set $\uparrow\downarrow$
LB1		WebCluster1 (10.1.3.80)	AS1
LB2		WebCluster1 (10.1.3.81)	AS1

- Click Add again to confirm your selection
- All settings will now be validated and the Backend Pool will be created



Note If you have multiple VIPs on different IPs you'll need to setup a Backend Pool for each of these. This is illustrated in the diagram in Implementing HA in Azure.

3. Next, create a Health Probe.

- In the menu for the Load balancer, click Health-probes
- Click Add

Name *	LB-Probe	
Protocol *	НТТР	\sim
Port * 🕡	6694	 ✓
Path * 🕕	/	✓
Interval * 🗊	5	
		seconds
Unhealthy threshold * 🕕	2	
		consecutive failures
Used by 🛈	Not used	

- Enter an appropriate name, e.g. LB-Probe
- Set Protocol to HTTP

Note

Setting Protocol to HTTP will configure the Azure load balancer to look for a 200 OK response from each Loadbalancer.org VM.

- Set Port to 6694
- Leave the remaining settings at their default values
- Click OK

Note The same Health probe should be used across all Load balancing rules.

- 4. Next, configure the Load Balancing Rule.
 - In the menu for the Load balancer, click Load balancing rules
 - Click Add

Name *	WebCluster1-80	~
IP Version *	● IPv4 ○ IPv6	
Frontend IP address * 🥡	LoadBalancerFrontEnd (51.132.22.253)	\sim
Protocol	• TCP UDP	
Port *	80	~
Backend port * 🛈	80	~
Backend pool * 🗊	WebCluster1	\sim
Health probe * 🛈	LB-Probe (HTTP:6694)	\sim
Session persistence ①	None	\sim
Idle timeout (minutes) * 🔋	0	4
Floating IP 🛈	● Disabled ○ Enabled	

- Enter an appropriate Name, e.g. WebCluster1-80
- Select the required IP version, e.g. IPv4
- Select the required Frontend IP address
- Set the Protocol to TCP
- Set the Port to the required value, e.g. 80
- Set the Backend port to the required value, e.g. 80
- Select the Backend pool created previously
- Select the Health Probe created previously
- Leave Session persistence set to None session persistence is not required since the Azure Load balancer will simply send all traffic to the working Loadbalancer.org appliance, i.e the appliance that is responding with a 200 OK to the HTTP probe on TCP port 6694
- Click Add

Note

If your configuration includes other ports (e.g. HTTPS port 443) or if you have multiple VIPs you'll need to setup multiple *Load balancing rules* to map from the Azure load balancer's Frontend IP to the appropriate *Backend Pool* and appropriate port. Also, you may need to setup multiple *Frontend IP Configurations & Backend Pools* depending on whether your VIPs share the same IP or have unique IP addresses, and whether the load balanced servers are common between VIPs or unique. The same *Health-probe* should be used for all *Load balancing rules*. This is illustrated in the diagram in Implementing HA in Azure.

5. Next, configure the Inbound NAT Rules (if required) to enable VM access via the Azure Load balancer.

Each load balancer retains it's original public IP address by default and this is displayed in the *Azure Portal > Home > Virtual Machines* page in the *Public IP Address* column. If you continue to drill down into each VM, the *same* Public IP address is shown for both load balancers, this is the Front end IP address of the Azure load balancer.

Note If preferred, the individual IP addresses can be removed, leaving just the front end IP address of the load balancer. In this case, NAT rules can be used to provide access to the individual load balancer VM's that are located behind the Azure load balancer in an HA configuration.

The example below shows how to setup a rule to allow SSH access (TCP port 22) to the Primary Loadbalancer.org VM via the Azure load balancer public IP address on TCP port 122.

- In the menu for the Load balancer, click Inbound NAT rules
- Click Add

Name *	LB1-SSH]
Frontend IP address * 🕡	LoadBalancerFrontEnd (51.132.22.253)]
IP Version (i)	IPv4	
Service *	Custom]
Protocol	• TCP UDP	
Idle timeout (minutes) 🕕	O 4]
	Max: 3)
Port *	122 🗸]
Target virtual machine	LB1 (QS-RG1) V]
Network IP configuration 🕕	ipconfig1 (10.1.3.8)]
Port mapping (i)	🔘 Default 💿 Custom	
Floating IP 🕕	Disabled Enabled	
Target port *	22 🗸]

- Enter an appropriate name, e.g. LB1-SSH
- Ensure the Frontend IP address is set to the correct address (IP's from other Azure Load balancers will be included in the list)
- Set Service to Custom
- Set Protocol to TCP
- Set Port to 122
- Set Target Virtual Machine to the Primary Loadbalancer.org appliance, e.g. LB1
- Set Network IP Configuration to the Interface on the Primary Loadbalancer.org appliance

- Set Port Mapping to Custom
- Set Target port to 22
- Click Add

Note	Don't forget to modify the inbound rules on the appropriate Network Security Group to allow connections to the relevant target port, in this example TCP port 22.
Note	Rules to access other Loadbalancer.org management ports can be added as required. The table below shows example rules and ports that can be configured to access SSH and the WebUI on both appliances. The configuration for the first rule listed is covered above.

Example rules for Primary and Secondary management

The table below shows example NAT rules that can be used to enable access to SSH and the WebUI on both the Primary and Secondary appliances.

Rule Name	Port	Target Port	Use
LB1-SSH	122	22	external access to SSH on LB1
LB2-SSH	222	22	external access to SSH on LB2
LB1-WebUI	19443	9443	external access to WebUI on LB1
LB2-WebUI	29443	9443	external access to WebUI on LB2

Step 6 – Configure the HA Clustered Pair

- 1. Open the WebUI on the Primary appliance.
- 2. Navigate to: Cluster Configuration > High Availability Configuration.

11 A.	loadbalancer	Local IP address	
***	(Gatharicer or)	10.1.3.8	~
		IP address of new peer	
		10.1.3.9	
		Password for loadbalancer user on peer	
		Add new node	

- 3. In the *IP address of new peer* field, enter the Secondary appliance's private IP address.
- 4. In the *Password for loadbalancer user on peer* field enter the relevant password, the default password is 'loadbalancer'.
- 5. Click Add new node.

6. Once the pairing configuration has finished, any service restart messages and the confirmed pair message will be displayed as shown below:

The configura changes	ation of the following s	ervices has been changed. When reconfig	uration is complete, restart/reload the services to commit th
		Restart Heartbeat	
igh Availa	bility Configurat	tion - primary	
igh Availa	10.1.3.8	loadbalancer org	Break Clustered Pair

7. Restart the services using the buttons presented, in this case Heartbeat.

Step 7 – Configure the Primary appliance to allow service control during failover / fail-back

1. On the Primary appliance, navigate to: *Cluster configuration > Floating IPs*.

2. In the *New Floating IP* field define an unused IP address in the same subnet as the appliances – this address is not used for any connections, it's required to allow service control on both Primary & Secondary units.

Note The chosen IP address should not be in use anywhere else in the deployment.

3. Click Add Floating IP.

Step 8 – Configure the Virtual Service (VIP)

Note If you plan on adding a custom Layer manual 7 VIP please see Configuration Example 3.

- 1. On the Primary appliance, navigate to: *Cluster Configuration > Layer 7 Virtual Services* and click **Add a New Virtual Service**.
- 2. Enter the following details:

Virtual Service			
Manual Configuration			0
Label	WebCluster1		0
IP Address	10.1.3.80 🗸		0
Slave IP Address	10.1.3.81 🗸		0
Ports	80		0
Protocol			
Layer 7 Protocol	HTTP Mode 🗸		0
		Cancel	Update

- 3. Enter an appropriate label for the VIP, e.g. WebCluster1.
- 4. Set the *IP Address* field to the IP address of the VIP when active on the *Primary* appliance (the same address as added earlier in steps 3 & 4), e.g **10.1.3.80**.
- 5. Set the *Secondary IP Address* field to the IP address of the VIP when active on the *Secondary* appliance (same address added earlier in steps 3 & 4), e.g **10.1.3.81**.

 Note
 To assign additional IP addresses to the appliance, use the WebUI option: Local

 Configuration > Network Interface Configuration. If an IP address is added, you'll also need

 to add the same IP address to the Network Interface on the load balancer VM via the Azure portal.

- 6. Set the Virtual Service Ports field to 80.
- 7. Leave Layer 7 Protocol set to HTTP.
- 8. Click Update.

Step 9 – Configure the Real Servers (RIPs)

- 1. On the Primary appliance, navigate to: *Cluster Configuration > Layer 7 Real Servers* and click **Add a new Real Server** next to the newly created VIP.
- 2. Enter the following details:

Label	Web1	0
Real Server IP Address	10.1.3.11	0
Real Server Port	80	0
Re-Encrypt to Backend		0
Weight	100	0
		Cancel Update

3. Enter an appropriate label for the RIP, e.g. Web1.

- 4. Change the Real Server IP Address field to the required IP address, e.g. 10.1.3.11.
- 5. Set the Real Server Port field to 80.
- 6. Click Update.
- 7. Repeat the above steps to add your other Web Server(s).

Step 10 – Verify synchronization state

1. Verify that the status on the Primary & Secondary is as follows:



Note For other possible states, please refer to Clustered Pair Diagnostics.

The Secondary can be made active by clicking [Advanced] in the green box, and then clicking the Take over button:

2019-07-09 15:14:50 UTC
(Advanced)

Step 11 – Testing & Verification

• Browse to the public IP address of the Azure load balancer on port 80 and port 443, i.e.

http://<Public IP Address of Azure Load Balancer>

and

https://<Public IP Address of Azure Load Balancer>

 To verify failover to the passive device (typically the Secondary) click the Take Over button on the passive device and verify that load balanced services are still available via the now active Secondary appliance – the failover time will depend on the settings for the health probe, but using default values it should complete in under 10 seconds.

2 – Load Balancing Web Servers, HA Configuration, 1 subnet, layer 7 with SSL Termination

This is similar to the first example with the addition of SSL termination on the load balancer. We generally recommend that SSL should be terminated on the backend servers rather than the load balancer for scalability

reasons, although in some cases terminating on the load balancer may be preferred. In this example, the Loadbalancer.org instances are deployed across 2 Availability Zones and a Standard SKU Azure load balancer is used to route connections to the active appliance.

Step 1 – Deploy 2 x Loadbalancer.org VMs – one to be the Primary, the other to be the Secondary

1. Please refer to Deploying Enterprise Azure From the Marketplace. Set the Availability Option to Availability Zone and set the Availability zone number according to your requirements. For example, select Availability Zone 1 for the Primary VM and Availability Zone 2 for the Secondary VM.

Note

Some Images may not be supported within certain Availability Zones. If this is the case, please click Select size and choose an alternative option. For example, the Standard_A1_v2 image can be used instead of the **Standard_A1** image.

Step 2 – Verify Network Security Group Settings

- 1. Ensure that your Network Security Group(s) permit the following communication between the 2 VMs:
 - TCP port 22 (SSH)
 - UDP port 6694 (heartbeat)
 - ICMP Ping

Note These requirements are covered by default within the same Virtual Network. Please refer to this link for more information on default rules.

- 2. Ensure that your Network Security Group(s) permit the following inbound communication from the Azure load balancer to both VMs:
 - TCP port 6694 (Azure load balancer health probe)



Note This requirement is covered by default within the same Virtual Network. Please refer to this link for more information on default rules.

Step 3 – Add the IP Address to be used for the VIP to the Primary & Secondary using the Azure Portal

- 1. In the Azure Portal select Virtual Machines.
- 2. Select the Primary VM.
- 3. Select Networking, then click the Network Interface.
- 4. Select IP Configurations.
- 5. Click Add.

Name ^	
WebCluster1	~
ype	
Primary Secondary	
Primary IP configuration already exists	
rivate IP address settings	
llocation	
Dynamic Static	
P address *	

Disassociate Associate

- Enter a suitable name for the IP address, e.g. WebCluster1
- Set Private IP address Allocation to Static
- Enter an appropriate IP address (this must tally with the address to be used for your VIP on the Loadbalancer.org appliance), e.g. 10.1.3.80
- Click OK
- Now repeat steps 1-5 on the Secondary VM for the VIP using a corresponding (but different) IP address, e.g. 10.1.3.81.

Step 4 – Add the IP Address to be used for the VIP to the Primary & Secondary using the Appliance WebUI

Primary Appliance

- On the Primary, navigate to the WebUI option: Local Configuration > Network Interface Configuration
- Add the IP you intend to use for the VIP, use CIDR notation, e.g. 10.1.3.80/24

Secondary Appliance

- On the Secondary, navigate to the WebUI option: Local Configuration > Network Interface Configuration
- Add the IP you intend to use for the VIP, use CIDR notation, e.g. 10.1.3.81/24

Step 5 – Add & Configure the Azure Load Balancer

- 1. First, add the Azure Load Balancer.
 - In the Azure Portal select Load balancers
 - Click Add

Subscription *	Loadbalancer.org Pay-As-You-Go
Resource group *	QS-RG1 V Create new
Instance details	
Name *	AzureLB
Region *	(Europe) UK South
Type * 🥡	🔘 Internal 💿 Public
SKU * 🥡	● Standard ─ Basic
	Intersection of the standard SKU load balancer for production workloads. Learn more about pricing differences between Standard and Basic SKU
Tier *	• Regional 🔘 Global
Public IP address	
Public IP address * 🕡	● Create new ○ Use existing
Public IP address name *	WebClusterPublicIP 🗸
Public IP address SKU	Standard
IP address assignment *	🔿 Dynamic 🔘 Static
Availability zone *	Zone-redundant \checkmark
Add a public IPv6 address 🕠	No Yes
Routing preference ①	● Microsoft network ○ Internet

- Configure the Subscription & Resource group settings according to your requirements
- Enter a suitable Name for the instance, e.g. AzureLB
- Select the required Region
- If deploying within a private network set *Type* to **Internal**, if it's public facing select **Public**
- Set SKU to Standard

This configuration example uses a **Standard** SKU Azure load balancer. **Configuration Example 1** uses a **Basic** SKU Azure load balancer. Please note the following when deciding which option to choose:

• If you have deployed your Primary & Secondary instances in an Availability Set then either the Basic or Standard SKU can be used

Note

- If you have deployed your Primary & Secondary instances using Availability Zones, then the Standard SKU must be used
- The Basic SKU is free, rates apply to the Standard SKU
- The Standard SKU has a published SLA, the Basic SKU does not
- Microsoft recommends the Standard SKU load balancer for production workloads

- Set the Tier according to your requirements
- Configure the Public IP address settings (for external deployments) or the Virtual Network settings (for internal deployments) according to your requirements

```
Note
```

Once the Azure Load balancer is created, the IP configuration can be modified using the *Frontend IP Configuration* in the Load balancer menu.

- If you have deployed your Primary and Secondary VM's in different Availability Zones, set Availability Zone to Zone Redundant, if you have deployed your VM's in the same Availability Zone, set Availability Zone to the same zone
- Click Next : Tags >
- Configure the Tags according to your requirements
- Click Next : Review + Create >
- Once validated, review the settings and click Create
- 2. Next, create the Backend Pool(s).
 - In the menu for the load balancer, click *Backend pools*
 - Click Add

Name *			
WebCluster1			~
Virtual network 🕠			
QS-RG1-VNET1 (QS-RG1)			\sim
Backend Pool Configuration			
O IP Address			
IP Version			
IPv4			
O IPv6			
Virtual machines			
You can only attach virtual machines configuration. All IP configurations n	in uksouth that have a standard SKU p nust be on the same virtual network.	ublic IP configuration or no public IP	
+ Add X Remove			
Virtual machine \uparrow_{\downarrow}	IP Configuration $~\uparrow\downarrow$	Availability set \uparrow_{\downarrow}	
No virtual machines selected			

- Enter an appropriate Name, e.g. WebCluster1
- Select the required Virtual Network
- Leave Backend Pool Configuration set to NIC
- Select the required IP version, e.g. IPv4

Click Add in the Virtual Machines section

🔎 Filter by name		Location == uksouth	Virtual network == C	S-RG1-VNET1
\blacksquare Virtual machine \uparrow_{\downarrow}	Resource group \uparrow_{\downarrow}	IP Configuration \uparrow_\downarrow	Availability set \uparrow_{\downarrow}	Tags
🔽 lb1	qs-rg1	WebCluster1 (10.1.3.80)	-	-
V lb2	qs-rg1	WebCluster1 (10.1.3.81)	-	-
lb1	qs-rg1	ipconfig1 (10.1.3.4)	-	-
lb2	qs-rg1	ipconfig1 (10.1.3.5)	-	-

- Ensure that both load balancer VMs are selected as shown in the example above (LB1 & LB2), and that the IP addresses selected correspond to the VIP on each appliance (10.1.3.80 & 10.1.3.81)
- Click Add

Virtual machines

You can only attach virtual machines in uksouth that have a standard SKU public IP configuration or no public IP configuration. All IP configurations must be on the same virtual network.

+ Add × Remove		
\Box Virtual machine \uparrow_\downarrow	IP Configuration \uparrow_{\downarrow}	Availability set $~\uparrow_\downarrow~$
lb2	WebCluster1 (10.1.3.81)	-
lb1	WebCluster1 (10.1.3.80)	-

- Click Add at the bottom of the screen to confirm your selections
- All settings will now be validated and the Backend Pool will be created

Note If you have multiple VIPs on different IPs you'll need to setup a Backend Pool for each of these. This is illustrated in the diagram in Implementing HA in Azure.

- 3. Next, create a Health Probe.
 - In the menu for the Load balancer, click Health-probes
 - Click Add

Name *	LB-Probe	\checkmark
Protocol *	НТТР	\sim
Port * 🗊	6694	~
Path * 🛈	/	✓
Interval * 🕕	5	
		seconds
Unhealthy threshold * 🛈	2	consocutivo failuros
		consecutive failures
Used by 🛈	Not used	

- Enter an appropriate name, e.g. LB-Probe
- Set Protocol to HTTP

```
Note
```

Setting *Protocol* to **HTTP** will configure the Azure load balancer to look for a **200 OK** response from each Loadbalancer.org VM.

- Set Port to 6694
- Leave the remaining settings at their default values
- Click OK

Note

The same Health probe should be used across all *Load balancing rules*.

- 4. Next, configure the Load Balancing Rule.
 - In the menu for the Load balancer, click Load balancing rules
 - Click Add

Name *	WebCluster1-80	~
IP Version *	● IPv4 ○ IPv6	
Frontend IP address * 🕕	LoadBalancerFrontEnd (20.49.171.40)	~
Protocol	● TCP ◯ UDP	
Port *	80	~
Backend port * 🕕	80	~
Backend pool * 🕕	WebCluster1	~
Health probe * 🛈	LB-Probe (HTTP:6694) Create new	~
Session persistence 🕕	None	~
Idle timeout (minutes) * 💿	0 4	ł
TCP reset	Disabled Enabled	
Floating IP 🕕	● Disabled ○ Enabled	
Outbound source network address translation (SNAT)	(Recommended) Use outbound rules to provide backend pool members access to the internet. Learn more □ ²	
	\bigcirc Use implicit outbound rule. This is not recommended because it can cause SNAT port exhaustion. Learn more ${\bf C}$	

- Enter an appropriate name, e.g. WebCluster1-80
- Select the required IP version, e.g. IPv4
- Select the required Frontend IP address
- Set the Protocol to TCP
- Set the Port to the required value, e.g. 80

- Set the Backend port to the required value, e.g. 80
- Select the Backend pool created previously
- Select the Health Probe created previously
- Leave Session persistence set to None session persistence is not required since the Azure Load balancer will simply send all traffic to the working Loadbalancer.org appliance, i.e the appliance that is responding with a 200 OK to the HTTP probe on TCP port 6694
- Leave the remaining settings at their default values
- Click OK

Note

If your configuration includes other ports (e.g. HTTPS port 443) or if you have multiple VIPs you'll need to setup multiple *Load balancing rules* to map from the Azure load balancer's Frontend IP to the appropriate *Backend Pool* and appropriate port. Also, you may need to setup multiple *Frontend IP Configurations* & *Backend Pools* depending on whether your VIPs share the same IP or have unique IP addresses, and whether the load balanced servers are common between VIPs or unique. The same *Health-probe* should be used for all *Load balancing rules*. This is illustrated in the diagram in Implementing HA in Azure.

5. Next, configure the Inbound NAT Rules (if required) to enable VM access via the Azure Load balancer.

Each load balancer retains it's original public IP address by default and this is displayed in the *Azure Portal > Home > Virtual Machines* page in the *Public IP Address* column. If you continue to drill down into each VM, the *same* Public IP address is shown for both load balancers, this is the Front end IP address of the Azure load balancer.

Note If preferred, the individual IP addresses can be removed, leaving just the front end IP address of the load balancer. In this case, NAT rules can be used to provide access to the individual load balancer VM's that are located behind the Azure load balancer in an HA configuration.

The example below shows how to setup a rule to allow SSH access (TCP port 22) to the Primary Loadbalancer.org VM via the Azure load balancer public IP address on TCP port 122.

- In the menu for the Load balancer, click Inbound NAT rules
- Click Add

Name *	LB1-SSH	<
Frontend IP address * (i)	LoadBalancerFrontEnd (null)	,
IP Version 🕕	IPv4	
Service *	Custom	,
Protocol	● TCP ◯ UDP	
Idle timeout (minutes) 🕕	0 4	
	Max: 3	30
Port *	122 ~	<
Port * Target virtual machine	122 V LB1 (QS-RG1) V	<u>_</u>
Port * Target virtual machine Network IP configuration ①	122 LB1 (QS-RG1) ipconfig1 (10.1.3.8)	-
Port * Target virtual machine Network IP configuration (i) Port mapping (i)	122 LB1 (QS-RG1) ipconfig1 (10.1.3.8) O Default (O Custom	
Port * Target virtual machine Network IP configuration ① Port mapping ① Floating IP (direct server return) ①	122 V LB1 (QS-RG1) V ipconfig1 (10.1.3.8) V O Default O Custom Image: O Disabled Image: O Disable	

- Enter an appropriate name, e.g. LB1-SSH
- Ensure the Frontend IP address is set to the correct address (IP's from other Azure Load balancers will be included in the list)
- Set Service to Custom
- Set Protocol to TCP
- Set Port to 122
- Set Target Virtual Machine to the Primary Loadbalancer.org appliance, e.g. LB1
- Set Network IP Configuration to the Interface on the Primary Loadbalancer.org appliance
- Set Port Mapping to Custom
- Set Target port to 22
- Click Add

Note

Note

Don't forget to modify the inbound rules on the appropriate Network Security Group to allow connections to the relevant target port, in this example TCP port 22.

Rules to access other Loadbalancer.org management ports can be added as required. The table below shows example rules and ports that can be configured to access SSH and the WebUI on both appliances. The configuration for the first rule listed is covered above.

Example rules for Primary and Secondary management

The table below shows example NAT rules that can be used to enable access to SSH and the WebUI on both the Primary and Secondary appliances.

Rule Name	Port	Target Port	Use
LB1-SSH	122	22	external access to SSH on LB1
LB2-SSH	222	22	external access to SSH on LB2
LB1-WebUI	19443	9443	external access to WebUI on LB1
LB2-WebUI	29443	9443	external access to WebUI on LB2

Step 6 – Configure the HA Clustered Pair

- 1. Open the WebUI on the Primary appliance.
- 2. Navigate to: Cluster Configuration > High Availability Configuration.

load balancer	Local IP address	
		10.1.3.8
		IP address of new peer
		10.1.3.9
		Password for loadbalancer user on peer
		Add new node

- 3. In the *IP address of new peer* field, enter the Secondary appliance's private IP address.
- 4. In the *Password for loadbalancer user on peer* field enter the relevant password, the default password is 'loadbalancer'.
- 5. Click Add new node.
- 6. Once the pairing configuration has finished, any service restart messages and the confirmed pair message will be displayed as shown below:



7. Restart the services using the buttons presented, in this case Heartbeat.

Step 7 – Configure the Primary appliance to allow service control during failover / fail-back

1. On the Primary appliance, navigate to: *Cluster configuration > Floating IPs*.

New Floating IP	10.1.3.100

2. In the *New Floating IP* field enter an unused IP address in the same subnet as the appliances – this address is not used for any connections, it's required to allow service control on both Primary & Secondary units.

dd Floating IP

3. Click Add Floating IP.

Step 8 – Configure the Virtual Service (VIP)

Note If you plan on adding a custom Layer manual 7 VIP please see Configuration Example 3.

- 1. On the Primary appliance, navigate to: *Cluster Configuration > Layer 7 Virtual Services* and click **Add a New Virtual Service**.
- 2. Enter the following details:

Virtual Service			
Manual Configuration			0
Label	WebCluster1		0
IP Address	10.1.3.80 🗸		0
Slave IP Address	10.1.3.81 🗸		0
Ports	80		0
Protocol			
Layer 7 Protocol	HTTP Mode 🗸		0
		Cancel	Update

- 3. Enter an appropriate label for the VIP, e.g. WebCluster1.
- 4. Set the *IP Address* field to the IP address of the VIP when active on the *Primary* appliance (the same address as added earlier in steps 3 & 4), e.g **10.1.3.80**.
- 5. Set the *Secondary IP Address* field to the IP address of the VIP when active on the *Secondary* appliance (same address added earlier in steps 3 & 4), e.g **10.1.3.81**.

Note

To assign additional IP addresses to the appliance, use the WebUI option: *Local Configuration* > *Network Interface Configuration*. If an IP address is added, you'll also need to add the same IP address to the Network Interface on the load balancer VM via the Azure portal.

- 1. Set the Virtual Service Ports field to 80.
- 2. Leave Layer 7 Protocol set to HTTP.
- 3. Click Update.

Step 9 – Configure the Real Servers (RIPs)

- 1. On the Primary appliance, navigate to: *Cluster Configuration > Layer 7 Real Servers* and click **Add a new Real Server** next to the newly created VIP.
- 2. Enter the following details:

Label	Web1	0
Real Server IP Address	10.1.3.11	0
Real Server Port	80	0
Re-Encrypt to Backend		0
Weight	100	0
		Cancel Update

- 3. Enter an appropriate label for the RIP, e.g. Web1.
- 4. Change the Real Server IP Address field to the required IP address, e.g. 10.1.3.11.
- 5. Set the *Real Server Port* field to 80.
- 6. Click Update.
- 7. Repeat the above steps to add your other Web Server(s).

Step 10 – Upload your SSL Certificate

- 1. Using the WebUI, navigate to: *Cluster Configuration > SSL Certificate* and click Add a new SSL Certificate.
- 2. Select Upload prepared PEM/PFX file.
- 3. Enter an appropriate label (name) for the certificate, e.g. Cert1.
- 4. Browse to and select the relevant certificate file.
- 5. for PFX files, enter the PFX File Password.
- 6. Click Add Certificate.

Note

You can also create a CSR on the load balancer. If this is required, select the *Create A New SSL Certificate (CSR)* option instead of *Upload prepared PEM/PFX file* in step 2 above. For additional information please refer to Generating a CSR on the Load Balancer.

Step 11 – Configure SSL Termination

1. Using the WebUI, navigate to: *Cluster Configuration > SSL Termination* and click Add a New Virtual Service.

Label	SSL-WebCluster1		0
IP Address	10.1.3.80 🗸		0
Slave IP Address	10.1.3.81 🗸		0
Virtual Service Port	443		0
Associated Virtual Service	WebCluster1 🗸		0
Backend Virtual Service Port	80		0
SSL Operation Mode	High Security		0
SSL Certificate	Cert1	•	0
		Cancel	Update

- 2. Enter a suitable label (name), e.g. SSL-WebCluster1.
- 3. Using the **IP Address** drop-down, set the address to the same address configured previously in Step 8 when active on the Primary, e.g. **10.1.3.80**.
- 4. Using the **Secondary IP Address** drop-down, set the address to the same address configured previously in Step 8 when active on the Secondary, e.g. **10.1.3.81**.
- 5. Set the Associated Virtual Service drop-down to the VIP created previously in Step 8.
- 6. Ensure the Backend Port is set to the same port that the VIP created previously listens on, e.g. 80.
- 7. Leave the SSL Operation Mode set to High Security.
- 8. Select the SSL Certificate uploaded in step (d) above.
- 9. Click Update.

Step 12 – Apply the New Settings

- Once the configuration is complete:
 - 1. use the **Reload HAProxy** button at the top of the screen to commit the changes.
 - 2. use the **Restart STunnel** button at the top of the screen to commit the changes.

Step 13 – Verify synchronization state

1. Verify that the status on the Primary & Secondary is as follows:

Primary Unit:



Note If no services have been configured, 'Active' will be grayed out on both instances.

The Secondary can be made active by clicking [Advanced] in the green box, and then clicking the Take over button:

System Overview 👔	2019-07-09 15:14:50 UTC
Information: This device is currently passive. Please see the active device for Virtual Service statistics.	(Advanced)

Note For other possible states, please refer to Clustered Pair Diagnostics.

Step 14 – Testing & Verification

• Browse to the public IP address of the Azure load balancer on port 80 and port 443, i.e.

http://<Public IP Address of Azure Load Balancer>

and

https://<Public IP Address of Azure Load Balancer>

 To verify failover to the passive device (typically the Secondary) click the Take Over button on the passive device and verify that load balanced services are still available via the now active Secondary appliance – the failover time will depend on the settings for the health probe, but using default values it should complete in under 10 seconds.

3 – Load Balancing Web Servers, HA Configuration, 1 subnet, layer 7 (Manual Configuration) with SSL Termination

The configuration used in the example is very similar to Example 2. The difference is that the layer 7 VIP and associated RIPs are configured using a Layer 7 'Manual Configuration'.

Custom, manually configured Layer 7 services are useful when your configuration requires advanced HAProxy settings that are not directly supported by the WebUI when creating and modifying VIPs & RIPs.

This example demonstrates the key point for manual layer 7 based services which is that an additional HAProxy **bind** directive must be added to the VIPs configuration. This additional bind directive allows the service to be brought up on a corresponding IP address on the Secondary appliance should a failover occur. Since this example also has an SSL termination, an **acl** directive also needs to be added to allow failover to the Save appliance as shown below.

- 1. Follow steps 1 to 7 in Configuration Example 2.
- 2. On the Primary appliance, navigate to: *Cluster Configuration > Layer 7 Virtual Services* and click Add a New Virtual Service.
- 3. Enter the following details:

Virtual Service			
Manual Configuration			0
Label	WebCluster1		0
IP Address	10.1.3.80 🗸		0
Slave IP Address	10.1.3.81 🗸		0
Ports	80		0
		Cancel	Update

- 4. Ensure that the *Manual Configuration* checkbox is ticked.
- 5. Enter an appropriate label for the VIP, e.g. WebCluster1.
- 6. Set the *IP Address* field to the IP address of the VIP when active on the *Primary* appliance (the same address as added earlier in steps 3 & 4), e.g **10.1.3.80**.
- 7. Set the Secondary IP Address field to the IP address of the VIP when active on the Secondary appliance (same address added earlier in steps 3 & 4), e.g **10.1.3.81**.
- 8. Set the Virtual Service Ports field to 80.
- 9. Click Update.
- 10. On the Primary appliance, navigate to: *Cluster Configuration > Layer 7 Real Servers* and click **Add a new Real Server** next to the newly created VIP.
- 11. Enter the following details:

Label	Web1	0
Real Server IP Address	10.1.3.11	0
Real Server Port	80	0
Re-Encrypt to Backend		0
Weight	100	0
		Cancel Update

- 12. Enter an appropriate label for the RIP, e.g. Web1.
- 13. Change the Real Server IP Address field to the required IP address, e.g. 10.1.3.11.
- 14. Set the Real Server Port field to 80.
- 15. Click Update.
- 16. Repeat the above steps to add your other Web Server(s).
- 17. Now navigate to: Cluster Configuration > Layer 7 Manual configuration.
- 18. Paste the following configuration into the edit window under the last line of text:

listen WebCluster1 bind 10.1.3.80:80 transparent bind 10.1.3.81:80 transparent <--- See Note 2 below mode http balance leastconn acl SSL-WebCluster1 src 10.1.3.80 acl SSL-WebCluster1 src 10.1.3.81 <--- See Note 3 below tcp-request connection expect-proxy layer4 if SSL-WebCluster1 cookie SERVERID maxidle 30m maxlife 12h insert nocache indirect server backup 127.0.0.1:9081 backup non-stick option http-keep-alive timeout http-request 5s option forwardfor timeout tunnel 1h option redispatch option abortonclose maxconn 40000 server Web1 10.1.3.11:80 weight 100 cookie web1 check inter 4000 rise 2 fall 2 slowstart 8000 minconn 0 maxconn 0 on-marked-down shutdown-sessions server Web2 10.1.3.12:80 weight 100 cookie web1 check inter 4000 rise 2 fall 2 slowstart 8000 minconn 0 maxconn 0 on-marked-down shutdown-sessions (1) This is an example, for more information please refer to Layer 7 - Custom Configurations Note

Note	(2) Additional bind statement for the VIP when active on the Secondary.
Note	(3) Additional SSL termination related ACL statement when active on the Secondary.
Note	(4) Make sure you use the <i>same</i> names, IP addresses and Ports as you did when graphically defining the VIP and RIPs.

- 19. Click Update.
- 20. Now follow steps **10** to **14** starting here.

4 – Load Balancing Web Servers, Single Appliance, 2 subnets, layer 4 NAT Mode

This example uses 2 subnets – one public subnet for the load balancer and one private subnet for the web servers. The load balancer has a single network interface located in the first subnet. Routing rules for the second private subnet must be changed so that return traffic passes back via the load balancer. This is achieved by creating a custom routing table with the required rules, then associating this with the private subnet – this can now be done directly in the portal (step 2 below), previously PowerShell had to be used.



This configuration is currently not supported in HA mode. In this mode, the custom routing rules would need to be dynamically modified to route via the Secondary appliance rather than the Primary if a failover occurs. This is currently not supported.

Step 1 – Setting up Azure

1) Deploy VM's & Configure Network Security Groups:

- 1. Deploy the load balancer instance into the first (public) subnet as described in Deploying Enterprise Azure From the Marketplace.
- 2. Deploy your required web server VMs into the second (private) subnet.
- 3. Configure Network Security Groups to permit the required traffic flows. Configure the following rules for the 2 subnets (assuming a public facing deployment):

- Load Balancer (Public) Subnet:
 - Inbound rule from 0.0.0.0/0 to port 80
 - Outbound rule from 0.0.0.0/0 to private subnet, port 80
- Web Server (Private) Subnet:
 - Inbound rule from 0.0.0.0/0 to port 80
- 4. Ensure that you add the private IP address to be used for the VIP to the VMs NIC using the Azure Portal, otherwise Azure will *not* be aware of this address.

2) Configure a Custom Routing Table

- 1. Using the search option at the top of the page, search for "Route tables".
- 2. Click Add.

Subscription * 🕕	Loadbalancer.org Pay-As-You-Go	\sim
Resource group * 🕕	QS-RG1	\sim
	Create new	
Instance details		
Region * 🛈	UK South	\sim
Name * 🗊	RT1	~
Propagate gateway routes * 🛈	 Yes No 	

- 3. Configure the Subscription, Resource group & Region settings according to your requirements.
- 4. Enter a suitable name for the Route table, e.g. RT1.
- 5. Click Next : Tags >.
- 6. Define any required tags.
- 7. Click Review Create.
- 8. Once created, select the newly created Route table.
- 9. Click Routes under Settings, click Add.

R1	~
* Address prefix 👩	
0.0.0/0	×
Next hop type 🚯	
Virtual appliance	~
* Next hop address 👩	
-	

- 10. Enter a suitable name for the route, e.g. **R1**.
- 11. Set the Address prefix to 0.0.0.0/0 (i.e. the default route).

respective network interface's IP address settings.

- 12. Set the next hop type to Virtual appliance.
- 13. Set the next hop address to the IP address of the load balancer in the public subnet, e.g. 10.1.6.5.
- 14. Click OK.



As mentioned in the note in the above screen shot, IP forwarding must be enabled for the load balancer VM. This is covered below in section 3).

- 15. Click Subnets under Settings.
- 16. Click Associate
- 17. Select the relevant VNet and the Private Subnet

Virtual network 🔅	
VNET1	\sim
Subnet ()	
S2	\sim

18. Click **OK**.

3) Enable IP Forwarding for the Load balancer VM:

- 1. In the Azure Portal main menu, select Virtual Machines.
- 2. Select the Load balancer VM and click *Networking* under Settings.
- 3. Click the Network Interface for the VM.
- 4. Click IP Configurations.
- 5. Ensure that *IP forwarding* is enabled as shown below:

IP forwarding settings

IP forwarding

Disabled Enabled

6. Click Save.

Step 2 – Configure the Virtual Service on the Load Balancer

- Using the WebUI, navigate to: Cluster Configuration > Layer 4 Virtual Services and click Add a New Virtual Service.
- 2. Enter the following details:

Virtual Service			
Label	Web-Cluster1		0
IP Address	10.1.6.40		0
Ports	80		0
Protocol			
Protocol	ТСР	~	0
Forwarding			
Forwarding Method	NAT 🗸		0
			Cancel Update

- 3. Enter an appropriate label for the VIP, e.g. Web-Cluster1.
- 4. Set the Virtual Service IP Address field to an appropriate value, e.g. 10.1.6.40.
- 5. Set the Virtual Service Ports field to 80.
- 6. Leave Protocol set to TCP.
- 7. Ensure Forwarding Method is set to NAT.
- 8. Click Update.

Step 3 – Setting up the Real Servers

- 1. Using the WebUI, navigate to: *Cluster Configuration* > *Layer 4 Real Servers* and click Add a new Real Server next to the newly created VIP.
- 2. Enter the following details:

Label	Web1		0
Real Server IP Address	10.1.8.100		0
Real Server Port	80		0
Weight	100		0
Minimum Connections	0		0
Maximum Connections	0		0
		Cancel	Undate

- 3. Enter an appropriate label for the RIP, e.g. Web1.
- 4. Change the *Real Server IP Address* field to the required IP address, e.g. **10.1.8.100**.
- 5. Set the *Real Server Port* field to 80.
- 6. Click Update.
- 7. Repeat the above steps to add your other Web Server(s).

If you want your Real Severs to be able to access the outside world, i.e. the Internet in a public
facing deployment, outbound requests passing via the load balancer must be NAT'd so that the
source IP becomes the load balancer's own external address. This can be configured using the
WebUI menu option: Cluster Configuration > Layer 4 Advanced Configuration and setting the
Auto-NAT drop-down to eth0.

Step 4 – Assigning a Public IP Address

- For public facing deployments, you'll need to associate a Public IP address with the Private IP address used for the VIP. To associate a Public IP address with a Private address:
 - 1. Select the load balancer VM in the Azure Portal.
 - 2. Click Networking.
 - 3. Select the Network Interface.
 - 4. Select IP Configurations.
 - 5. Click the IP configuration for the VIP.
 - 6. Change Public IP address to **Enabled**.
 - 7. Select an existing available Public IP address or create a new one.
 - 8. Click Save.

Step 5 – Testing & Verification

• To test the configuration is working, browse to the public IP address or FQDN on HTTP port 80, i.e.

http://<Public IP Address>

5 – Load Balancing Web Servers, Single Appliance, 2 subnets, layer 7 with TProxy

This example is the same as the previous example with regard to network layout. It uses 2 subnets – one public subnet for the load balancer and one private subnet for the web servers. The load balancer has a single network interface located in the first subnet. Routing rules for the second private subnet must be changed so that return traffic passes back via the load balancer. This is achieved by creating a custom routing table with the required rules, then associating this with the private subnet.

In addition, Layer 7 transparency is enabled on the load balancer to ensure that the source IP address of packets reaching the web servers is the source IP of the clients and not the IP address of the load balancer.

Note

This configuration is currently not supported in HA mode. In this mode, the custom routing rules would need to be dynamically modified to route via the Secondary appliance rather than the Primary if a failover occurs. This is currently not supported.

Step 1 – Setting up Azure

Follow steps 1 to 3 in the "Setting up Azure" section of Configuration Example 3.

Step 2 – Configure the Virtual Service on the Load Balancer

- Using the WebUI, navigate to: Cluster Configuration > Layer 7 Virtual Services and click Add a New Virtual Service.
- 2. Enter the following details:

Virtual Service			
Manual Configuration			0
Label	Web-Cluster1		0
IP Address	10.6.1.40		0
Ports	80		0
Protocol			
Layer 7 Protocol	HTTP Mode 🗸		0
		Cancel	Update

- 3. Enter an appropriate label for the VIP, e.g. Web-Cluster1.
- 4. Set the Virtual Service IP Address field to an appropriate value, e.g. 10.1.6.40.
- 5. Set the Virtual Service Ports field to 80.
- 6. Leave *Protocol* set to **HTTP Mode**.
- 7. Click Update.
- 8. Now click **Modify** next to the newly created VIP.
- 9. Scroll down to the 'Other' section, click [Advanced], scroll to the bottom and enable (check) Transparent Proxy.

10. Click Update.

Step 3 – Setting up the Real Servers

- 1. Using the WebUI, navigate to: *Cluster Configuration > Layer 7 Real Servers* and click **Add a new Real Server** next to the newly created VIP.
- 2. Enter the following details:

Label	Web1		0
Real Server IP Address	10.1.6.100		0
Real Server Port	80		0
Re-Encrypt to Backend			0
Weight	100		0
		Cancel	Update

- 3. Enter an appropriate label for the RIP, e.g. Web1.
- 4. Change the *Real Server IP Address* field to the required IP address, e.g. **10.1.8.100**.
- 5. Set the Real Server Port field to 80.
- 6. Click Update.

Note

7. Repeat the above steps to add your other Web Server(s).

If you want your Real Severs to be able to access the outside world, i.e. the Internet in a public facing deployment, outbound requests passing via the load balancer must be NAT'd so that the source IP becomes the load balancer's own external address. This can be configured using the WebUI menu option: *Cluster Configuration > Layer 4 Advanced Configuration* and setting the *Auto-NAT* drop-down to **eth0**.

Step 4 – Assigning a Public IP Address

- For public facing deployments, you'll need to associate a Public IP address with the Private IP address used for the VIP. To associate a Public IP address with a Private address:
 - 1. Select the load balancer VM in the Azure Portal.
 - 2. Click Networking.
 - 3. Select the Network Interface.
 - 4. Select IP Configurations.
 - 5. Click the IP configuration for the VIP.
 - 6. Change Public IP address to **Enabled**.
 - 7. Select an existing available Public IP address or create a new one.
 - 8. Click Save.

Step 5 – Testing & Verification

• To test the configuration is working, browse to the public IP address or FQDN on HTTP port 80, i.e.

http://<Public IP Address>

or

http://<FQDN>

9. Testing – General Comments

Note

For additional guidance on diagnosing and resolving any issues you may have, please also refer to Diagnostics & Troubleshooting.

Testing Load Balanced Services

For example, to test a web server based configuration, add a page to each web servers root directory e.g. *test.html* and put the server name on this page for easy identification during the tests.

Use two or more clients to do the testing. Open up a web browser on each test clients and enter the URL for the VIP e.g. http://104.40.133.119

Provided that persistence is disabled, each client should see a different server name because of the load balancing algorithm in use, i.e. they are being load balanced across the cluster.

Why test using two clients? - If you use a single client it will most likely keep on hitting the same server for multiple requests. This is to do with the way that the load balancing algorithms are optimized.

Diagnosing VIP Connection Problems

 Make sure that the device is active – this can be checked in the WebUI. For a single appliance, the status bar should report Primary & Active as shown below:



 Check that the VIP(s)/floating IP(s) are up – Using View Configuration > Network Configuration verify that the VIP is active on the load balancer, if not check Logs > Heartbeat for errors.

```
2: eth0: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP qlen 1000
link/ether 00:0c:29:cf:18:03 brd ff:ff:ff:ff:ff
inet 192.168.110.85/18 brd 192.168.127.255 scope global eth0
valid_lft forever preferred_lft forever
inet 192.168.110.90/18 brd 192.168.127.255 scope global secondary eth0
valid_lft forever preferred_lft forever
```

The above example shows that the interface address (192.168.110.85) and the VIP address (192.168.110.90) are both up.

3. Check that the Real Servers are up – Using System Overview make sure that none of your VIPs are colored red. If they are, the entire cluster is down (i.e. all Real Servers). Green indicates a healthy cluster, yellow

indicates that your cluster may need attention (one or more of the Real Servers may be down), and blue indicates all Real Server have been deliberately taken offline (by using either Halt or Drain).

System C	Overview 😮					2015	5-03-18 11:37	:15 UTC
	VIRTUAL SERVICE \$	IP 🗢	PORTS 🗢	CONNS 🗢	PROTOCOL \$	METHOD \$	MODE 🗢	
1	HTTP-Cluster	192.168.110.150	80	0	HTTP	Layer 7	Proxy	8 <i>41</i>
A	RDP-Cluster	192.168.110.150	3389	0	ТСР	Layer 7	Proxy	W
+	HTTP-Cluster-2	192.168.110.152	80	0	HTTP	Layer 7	Proxy	8 <i>4</i> 1
٢	RDP-Cluster-2	192.168.110.152	3389	0	тср	Layer 7	Proxy	M

4. Check the connection state:

- For layer 4 NAT mode VIPs, check Reports > Layer 4 Current Connections to view the current traffic in detail. Any packets with state SYN_RECV often implies a return traffic routing issue:
 - For single subnet Layer 4 mode make sure that the default gateway on all real servers is set to be the load balancer
 - For dual subnet Layer 4 mode make sure that routing on the second subnet has been configured correctly
- For Layer 7 VIPs, the Layer 7 statistics page can be used. To access the page, navigate to: Reports > Layer 7 Status - a new tabbed window will be displayed:

> Gene	ral	oror	ess	inf	orm	ation																						
pid = 3261 (process #1, nbproc = 1) uptime = 0d 0h00m42s system limits: mermax = unlimited; ulimit-n = 81000 maxsock = 80024; maxconn = 40000; maxpipes = 0 current coms = 1; current pipes = 0/0; conn rate = 2/sec Running tasks: 1/5; idle = 100 %						a a a a a a a a a a a a a a a a a a a	active UP backup UP active UP, going down active DOWN, going up active or backup DOWN or backup DOWN, going up active or backup DOWN or maintenance (MAINT) te: UP with load-balancing disabled is reported as "NOLB".								Display option: Hide "DOWN servers Refresh now CSV export				15	External ressources: Primary site Updates (v1.5) Online manual								
		Queu	e	Ses	sion	rate		Ses	sions			By	tes	Der	nied		Errors		Warn	ings				Serv	/er			
	Cur	Max	Limit 0	Cur	Max	Limit C	ur Ma	x Lin	nit To	tal Lb	Tot	In	Out	Req	Resp	Req	Conn	Resp	Retr	Redis	Status	LastChk	Wgl	nt Act	Bck	Chk D	vn Dwntme	Thrtle
Frontend				0	15	-	0	4 40 0	000	56	2	21 696	3 385 782	0	0	0					OPEN							
backup	0	0		0	0		0	0	-	0	0	0	0		0		0	0	0	0			1	-	Y			
RIP1	0	0	-	0	16		0	2		56	56 2	21 696	3 385 782		0		0	0	0	0	42s UP	L4OK in 0ms	1	Y	-	0	0 0	5 -
Backend	0	0		0	16		0	2 4 (000	58	56 2	21 696	3 385 782	0	0		0	0	0	0	42s UP		1	1	1		0 0	5
sta	ts																											
		Que	ue	S	essio	n rate		S	ession	15		B	ytes	Den	ied		Errors	łe.	Wa	nings				Sei	ver			
	Cur	Max	Limit	Cu	Ma	x Limit	Cur	Max	Limit	Total	LbTot	In	Out	Req	Resp	Req	Conn	Resp	Retr	Redis	Status	LastChk	Wght	Act I	Bck	Chk Dw	n Dwntme	Thrtle
Frontend				1		4 -	1	1	2 000	8		1 464	33 111	0	0	4					OPEN	7						

Statistics Report for pid 3261

Taking Real Servers Offline

- 1. Using the *System Overview* check that when you Halt one of the Real Servers the connections are redirected to the other server in the cluster.
- Stop the web service/process on one of the servers, wait a few seconds (for the load balancer to detect the change) and then refresh the browsers on both clients. They should now both switch to the same server (since one has been removed from the load balancing list). Also check that the server is shown red (down) in the system overview.
- Start the web service/process on the server, wait a few seconds and then refresh the browsers again. After a few refreshes they should again show different web servers. Also check that the server is shown green (up) in the system overview.

The System Overview shows the status as these tests are performed:

STEM C	VERVIEW (2)					20	015-04-30 08:35	5:41 UT
	VIRTUAL SERVICE \$	IP 🖨	PORTS \$	CONNS 🕈	PROTOCOL \$	METHOD	MODE 🕈	
A	HTTP-Cluster	192.168.110.150	80	0	нттр	Layer 7	Proxy	1.M
	REAL SERVER	IP	PORTS	WEIGHT	CONNS			
1	RIP1	192.168.110.240	80	100	0	Drain	Halt	<u> </u>
0	RIP2	192.168.110.241	80	0	0	Online (h	alt)	Ŵ
	RIP3	192.168.110.242	80	100	0	Drain	Halt	1011

In this example:

RIP1 is green, this indicates that it's operating normally.

RIP2 is blue, this indicates that it has been either Halted or Drained. in this example Halt has been used as indicated by Online (Halt) being displayed. If it had been drained it would show as Online (Drain).

RIP3 is red, this indicates that it has failed a health check.

Using Reports & Log Files

The appliance includes several logs and reports that are very useful when diagnosing issues. Both are available as main menu options in the WebUI. Details of both can be found in Appliance Monitoring.

10. More Information

Please refer to our website for all the latest Manuals and Deployment Guides.

11. Loadbalancer.org Technical Support

If you have any questions regarding the appliance or need assistance with load balancing your application, please don't hesitate to contact support@loadbalancer.org.

About Loadbalancer.org

Loadbalancer.org's mission is to ensure that its clients' businesses are never interrupted. The load balancer experts ask the right questions to get to the heart of what matters, bringing a depth of understanding to each deployment. Experience enables Loadbalancer.org engineers to design less complex, unbreakable solutions - and to provide exceptional personalized support.



United Kingdom

Loadbalancer.org Ltd. Compass House, North Harbour Business Park, Portsmouth, PO6 4PS UK:+44 (0) 330 380 1064 sales@loadbalancer.org support@loadbalancer.org

United States

Loadbalancer.org, Inc. 4550 Linden Hill Road, Suite 201 Wilmington, DE 19808, USA TEL: +1 833.274.2566 sales@loadbalancer.org support@loadbalancer.org

Canada

Loadbalancer.org Appliances Ltd. 300-422 Richards Street, Vancouver, BC, V6B 2Z4, Canada TEL:+1 866 998 0508 sales@loadbalancer.org support@loadbalancer.org

Germany

Loadbalancer.org GmbH Tengstraße 2780798, München, Germany TEL: +49 (0)89 2000 2179 sales@loadbalancer.org support@loadbalancer.org